



# **INTEL® OPEN IMAGE DENOISE**

## **HIGH-PERFORMANCE DENOISING LIBRARY FOR RAY TRACING**

---

Version 0.8.1  
February 2, 2019

# Contents

<b>1</b>	<b>Open Image Denoise Overview</b>	<b>3</b>
1.1	Support and Contact . . . . .	3
1.2	Version History . . . . .	3
<b>2</b>	<b>Building Open Image Denoise from Source</b>	<b>5</b>
2.1	Prerequisites . . . . .	5
2.2	Compiling Open Image Denoise on Linux/macOS . . . . .	6
2.3	Compiling Open Image Denoise on Windows . . . . .	6
<b>3</b>	<b>Open Image Denoise API</b>	<b>8</b>
3.0.1	C99 API Example . . . . .	8
3.0.2	C++11 API Example . . . . .	9
3.1	Device . . . . .	9
3.1.1	Error Handling . . . . .	10
3.2	Buffer . . . . .	11
3.2.1	Data Format . . . . .	12
3.3	Filter . . . . .	13
3.3.1	RT . . . . .	14
<b>4</b>	<b>Examples</b>	<b>15</b>
4.1	Denoise . . . . .	15

# Chapter 1

## Open Image Denoise Overview

Intel® Open Image Denoise is a collection of high-performance, high-quality denoising filters for images rendered with ray tracing. Open Image Denoise is part of the [Intel Rendering Framework](#) and is released under the permissive [Apache 2.0 license](#).

The purpose of Open Image Denoise is to provide an open, high-quality, efficient, and easy-to-use denoising library that allows one to significantly reduce rendering times in ray tracing based rendering applications. It filters out the Monte Carlo noise inherent to stochastic ray tracing methods like path tracing, reducing the amount of necessary samples per pixel by even multiple orders of magnitude (depending on the desired closeness to the ground truth).

Open Image Denoise supports Intel® 64 architecture based CPUs and compatible architectures, and runs on anything from laptops, to workstations, to compute nodes in HPC systems. It is efficient enough to be suitable not only for offline rendering, but, depending on the hardware used, also for interactive ray tracing.

Open Image Denoise internally builds on top of [Intel® Math Kernel Library for Deep Neural Networks \(MKL-DNN\)](#), and fully exploits modern instruction sets like Intel SSE4, AVX2, and AVX-512 to achieve high denoising performance. A CPU with support for at least SSE4.1 is required to run Open Image Denoise.

### Support and Contact

Open Image Denoise is under active development, and though we do our best to guarantee stable release versions a certain number of bugs, as-yet-missing features, inconsistencies, or any other issues are still possible. Should you find any such issues please report them immediately via the [Open Image Denoise GitHub Issue Tracker](#) (or, if you should happen to have a fix for it, you can also send us a pull request); for missing features please contact us via email at [openimagedenoise@googlegroups.com](mailto:openimagedenoise@googlegroups.com).

For recent news, updates, and announcements, please see our complete [news/updates](#) page.

Join our [mailing list](#) to receive release announcements and major news regarding Open Image Denoise.

### Version History

#### Changes in v0.8.1:

- Fixed wrong path to TBB in the generated CMake configs
- Fixed wrong rpath in the binaries

- Fixed compile error on some macOS systems
- Fixed minor compile issues with Visual Studio
- Lowered the CPU requirement to SSE4.1
- Minor example update

### Changes in v0.8.0:

- Initial beta release

# Chapter 2

## Building Open Image Denoise from Source

The latest Open Image Denoise sources are always available at the [Open Image Denoise GitHub repository](#). The default master branch should always point to the latest tested bugfix release.

### Prerequisites

Open Image Denoise currently supports 64-bit Linux, Windows, and macOS operating systems. In addition, before you can build Open Image Denoise you need the following prerequisites:

- You can clone the latest Open Image Denoise sources via:

```
git clone --recursive https://github.com/OpenImageDenoise/oidn.git
```

- To build Open Image Denoise you need [CMake](#) 3.1 or later, a C++11 compiler (we recommend using Clang, but also support GCC, Microsoft Visual Studio 2015 or later, and [Intel® C++ Compiler](#) 17.0 or later), and Python 2.7 or later.
- Additionally you require a copy of [Intel® Threading Building Blocks](#) (TBB) 2017 or later.

Depending on your Linux distribution you can install these dependencies using yum or apt-get. Some of these packages might already be installed or might have slightly different names.

Type the following to install the dependencies using yum:

```
sudo yum install cmake
sudo yum install tbb-devel
```

Type the following to install the dependencies using apt-get:

```
sudo apt-get install cmake-curses-gui
sudo apt-get install libtbb-dev
```

Under macOS these dependencies can be installed using [MacPorts](#):

```
sudo port install cmake tbb
```

Under Windows please directly use the appropriate installers or packages for [CMake](#), [Python](#), and [TBB](#).

## Compiling Open Image Denoise on Linux/macOS

Assuming the above prerequisites are all fulfilled, building Open Image Denoise through CMake is easy:

- Create a build directory, and go into it

```
mkdir oidn/build
cd oidn/build
```

(We do recommend having separate build directories for different configurations such as release, debug, etc.).

- The compiler CMake will use by default will be whatever the CC and CXX environment variables point to. Should you want to specify a different compiler, run cmake manually while specifying the desired compiler. The default compiler on most Linux machines is gcc, but it can be pointed to clang instead by executing the following:

```
cmake -DCMAKE_CXX_COMPILER=clang++ -DCMAKE_C_COMPILER=clang ..
```

CMake will now use Clang instead of GCC. If you are OK with using the default compiler on your system, then simply skip this step. Note that the compiler variables cannot be changed after the first cmake or ccmake run.

- Open the CMake configuration dialog

```
ccmake ..
```

- Make sure to properly set the build mode and enable the components you need, etc.; then type 'c'onfigure and 'g'enerate. When back on the command prompt, build it using

```
make
```

- You should now have libOpenImageDenoise.so as well as a set of example applications.

## Compiling Open Image Denoise on Windows

On Windows using the CMake GUI (cmake-gui.exe) is the most convenient way to configure Open Image Denoise and to create the Visual Studio solution files:

- Browse to the Open Image Denoise sources and specify a build directory (if it does not exist yet CMake will create it).
- Click “Configure” and select as generator the Visual Studio version you have (Open Image Denoise needs Visual Studio 14 2015 or newer), for Win64 (32-bit builds are not supported), e.g., “Visual Studio 15 2017 Win64”.
- If the configuration fails because some dependencies could not be found then follow the instructions given in the error message, e.g., set the variable TBB\_ROOT to the folder where TBB was installed.
- Optionally change the default build options, and then click “Generate” to create the solution and project files in the build directory.
- Open the generated OpenImageDenoise.sln in Visual Studio, select the build configuration and compile the project.

Alternatively, Open Image Denoise can also be built without any GUI, entirely on the console. In the Visual Studio command prompt type:

```
cd path\to\oidn
mkdir build
cd build
cmake -G "Visual Studio 15 2017 Win64" [-D VARIABLE=value] ..
cmake --build . --config Release
```

Use `-D` to set variables for CMake, e.g., the path to TBB with “`-D TBB_ROOT=\path\to\tbb`”.

# Chapter 3

## Open Image Denoise API

Open Image Denoise provides a C99 API (also compatible with C++) and a C++11 wrapper API as well. For simplicity, this document mostly refers to the C99 version of the API.

The API is designed in an object-oriented manner, e.g. it contains device objects (OIDNDevice type), buffer objects (OIDNBuffer type), and filter objects (OIDNFilter type). All objects are reference-counted, and handles can be released by calling the appropriate release function (e.g. `oidnReleaseDevice`) or retained by incrementing the reference count (e.g. `oidnRetainDevice`).

An important aspect of objects is that setting their parameters do not have an immediate effect (with a few exceptions). Instead, objects with updated parameters are in an unusable state until the parameters get explicitly committed to a given object. The commit semantic allows for batching up multiple small changes, and specifies exactly when changes to objects will occur.

All API calls are thread-safe, but operations that use the same device will be serialized, so the amount of API calls from different threads should be minimized.

To have a quick overview of the C99 and C++11 APIs, see the following simple example code snippets.

### C99 API Example

```
#include <OpenImageDenoise/oidn.h>
...
// Create an Open Image Denoise device
OIDNDevice device = oidnNewDevice(OIDN_DEVICE_TYPE_DEFAULT);
oidnCommitDevice(device);

// Create a denoising filter
OIDNFilter filter = oidnNewFilter(device, "RT"); // generic ray tracing filter
oidnSetSharedFilterImage(filter, "color", colorPtr,
    OIDN_FORMAT_FLOAT3, width, height, 0, 0, 0);
oidnSetSharedFilterImage(filter, "albedo", albedoPtr,
    OIDN_FORMAT_FLOAT3, width, height, 0, 0, 0); // optional
oidnSetSharedFilterImage(filter, "normal", normalPtr,
    OIDN_FORMAT_FLOAT3, width, height, 0, 0, 0); // optional
oidnSetSharedFilterImage(filter, "output", outputPtr,
    OIDN_FORMAT_FLOAT3, width, height, 0, 0, 0);
oidnSetFilter1b(filter, "hdr", true); // image is HDR
oidnCommitFilter(filter);

// Filter the image
oidnExecuteFilter(filter);
```



```
// Check for errors
const char* errorMessage;
if (oidnGetDeviceError(device, &errorMessage) != OIDN_ERROR_NONE)
    printf("Error: %s\n", errorMessage);

// Cleanup
oidnReleaseFilter(filter);
oidnReleaseDevice(device);
```

## C++11 API Example

```
#include <OpenImageDenoise/oidn.hpp>
...
// Create an Open Image Denoise device
oidn::DeviceRef device = oidn::newDevice();
device.commit();

// Create a denoising filter
oidn::FilterRef filter = device.newFilter("RT"); // generic ray tracing filter
filter.setImage("color", colorPtr, oidn::Format::Float3, width, height);
filter.setImage("albedo", albedoPtr, oidn::Format::Float3, width, height); // optional
filter.setImage("normal", normalPtr, oidn::Format::Float3, width, height); // optional
filter.setImage("output", outputPtr, oidn::Format::Float3, width, height);
filter.set("hdr", true); // image is HDR
filter.commit();

// Filter the image
filter.execute();

// Check for errors
const char* errorMessage;
if (device.getError(errorMessage) != oidn::Error::None)
    std::cout << "Error: " << errorMessage << std::endl;
```

## Device

Open Image Denoise supports a device concept, which allows different components of the application to use the Open Image Denoise API without interfering with each other. An application first needs to create a device with

```
OIDNDevice oidnNewDevice(OIDNDeviceType type);
```

where the type enumeration maps to a specific device implementation, which can be one of the following:

Name	Description
OIDN_DEVICE_TYPE_DEFAULT	select the approximately fastest device
OIDN_DEVICE_TYPE_CPU	CPU device (requires SSE4.1 support)

**Table 3.1** – Supported device types, i.e., valid constants of type `OIDNDeviceType`.

Once a device is created, you can call

```
void oidnSetDevice1b(OIDNDevice device, const char* name, bool value);
void oidnSetDevice1i(OIDNDevice device, const char* name, int value);
bool oidnGetDevice1b(OIDNDevice device, const char* name);
int oidnGetDevice1i(OIDNDevice device, const char* name);
```

to set and get parameter values on the device. Note that some parameters are constants, thus trying to set them is an error. See the tables below for the parameters supported by devices.

Type	Name	Description
const int	version	combined version number (major.minor.patch) with two decimal digits per component
const int	versionMajor	major version number
const int	versionMinor	minor version number
const int	versionPatch	patch version number

**Table 3.2** – Parameters supported by all devices.

Type	Name	Default	Description
int	numThreads	0	maximum number of threads which Open Image Denoise should use; 0 will set it automatically to get the best performance
bool	setAffinity	true	bind software threads to hardware threads if set to true (improves performance); false disables binding

**Table 3.3** – Additional parameters supported only by CPU devices.

Note that the CPU device heavily relies on setting the thread affinities to achieve optimal performance, so it is highly recommended to leave this option enabled. However, this may interfere with the application if that also sets the thread affinities, potentially causing performance degradation. In such cases, the recommended solution is to either disable setting the affinities in the application or in Open Image Denoise, or to always set/reset the affinities before/after each parallel region in the application (e.g., if using TBB, with `tbb::task_arena` and `tbb::task_scheduler_observer`).

Once parameters are set on the created device, the device must be committed with

```
void oidnCommitDevice(OIDNDevice device);
```

This device can then be used to construct further objects, such as buffers and filters. Note that a device can be committed only once during its lifetime. Before the application exits, it should release all devices by invoking

```
void oidnReleaseDevice(OIDNDevice device);
```

Note that Open Image Denoise uses reference counting for all object types, so this function decreases the reference count of the device, and if the count reaches 0 the device will automatically get deleted. It is also possible to increase the reference count by calling

```
void oidnRetainDevice(OIDNDevice device);
```

An application typically creates only a single device. If required differently, it should only use a small number of devices at any given time.

## Error Handling

Each user thread has its own error code per device. If an error occurs when calling an API function, this error code is set to the occurred error if it stores no previous error. The currently stored error can be queried by the application via

```
OIDNError oidnGetDeviceError(OIDNDevice device, const char** outMessage);
```

where `outMessage` can be a pointer to a C string which will be set to a more descriptive error message, or it can be `NULL`. This function also clears the error code, which assures that the returned error code is always the first error occurred since the last invocation of `oidnGetDeviceError` on the current thread. Note that the optionally returned error message string is valid only until the next invocation of the function.

Alternatively, the application can also register a callback function of type

```
typedef void (*OIDNErrorFunction)(void* userPtr, OIDNError code, const char* message);
```

via

```
void oidnSetDeviceErrorFunction(OIDNDevice device, OIDNErrorFunction func, void* userPtr);
```

to get notified when errors occur. Only a single callback function can be registered per device, and further invocations overwrite the previously set callback function, which do *not* require also calling the `oidnCommitDevice` function. Passing `NULL` as function pointer disables the registered callback function. When the registered callback function is invoked, it gets passed the user-defined payload (`userPtr` argument as specified at registration time), the error code (code argument) of the occurred error, as well as a string (message argument) that further describes the error. The error code is always set even if an error callback function is registered. It is recommended to always set a error callback function, to detect all errors.

When the device construction fails, `oidnNewDevice` returns `NULL` as device. To detect the error code of a such failed device construction, pass `NULL` as device to the `oidnGetDeviceError` function. For all other invocations of `oidnGetDeviceError`, a proper device handle must be specified.

The following errors are currently used by Open Image Denoise:

**Table 3.4** – Possible error codes, i.e., valid constants of type `OIDNError`.

Name	Description
<code>OIDN_ERROR_NONE</code>	no error occurred
<code>OIDN_ERROR_UNKNOWN</code>	an unknown error occurred
<code>OIDN_ERROR_INVALID_ARGUMENT</code>	an invalid argument was specified
<code>OIDN_ERROR_INVALID_OPERATION</code>	the operation is not allowed
<code>OIDN_ERROR_OUT_OF_MEMORY</code>	not enough memory to execute the operation
<code>OIDN_ERROR_UNSUPPORTED_HARDWARE</code>	the hardware (e.g., CPU) is not supported

## Buffer

Large data like images can be passed to Open Image Denoise either via pointers to memory allocated and managed by the user (this is the recommended, often easier and more efficient approach, if supported by the device) or by creating buffer objects (supported by all devices). To create a new data buffer with memory allocated and owned by the device, holding `byteSize` number of bytes, use

```
OIDNBuffer oidnNewBuffer(OIDNDevice device, size_t byteSize);
```

The created buffer is bound to the specified device (device argument). The specified number of bytes are allocated at buffer construction time and deallocated when the buffer is destroyed.

It is also possible to create a “shared” data buffer with memory allocated and managed by the user with

```
OIDNBuffer oidnNewSharedBuffer(OIDNDevice device, void* ptr, size_t byteSize);
```

where ptr points to the user-managed memory and byteSize is its size in bytes. At buffer construction time no buffer data is allocated, but the buffer data provided by the user is used. The buffer data must remain valid for as long as the buffer may be used, and the user is responsible to free the buffer data when no longer required.

Similar to device objects, buffer objects are also reference-counted and can be retained and released by calling the following functions:

```
void oidnRetainBuffer(OIDNBuffer buffer);
void oidnReleaseBuffer(OIDNBuffer buffer);
```

Accessing the data stored in a buffer object is possible by mapping it into the address space of the application using

```
void* oidnMapBuffer(OIDNBuffer buffer, OIDNAccess access, size_t byteOffset, size_t byteSize)
```

where access is the desired access mode of the mapped memory, byteOffset is the offset to the beginning of the mapped memory region in bytes, and byteSize is the number of bytes to map. The function returns a pointer to the mapped buffer data. If the specified byteSize is 0, the maximum available amount of memory will be mapped. The access argument must be one of the access modes in the following table:

Name	Description
OIDN_ACCESS_READ	read-only access
OIDN_ACCESS_WRITE	write-only access
OIDN_ACCESS_READ_WRITE	read and write access
OIDN_ACCESS_WRITE_DISCARD	write-only access but the previous contents will be discarded

**Table 3.5** – Access modes for memory regions mapped with oidnMapBuffer, i.e., valid constants of type OIDNAccess.

After accessing the mapped data in the buffer, the memory region must be unmapped with

```
void oidnUnmapBuffer(OIDNBuffer buffer, void* mappedPtr);
```

where mappedPtr must be a pointer returned by a call to oidnMapBuffer for the specified buffer. Any change to the mapped data is guaranteed to take effect only after unmapping the memory region.

## Data Format

Buffers store opaque data and thus have no information about the type and format of the data. Other objects, e.g. filters, typically require specifying the format of the data stored in buffers or shared via pointers. This can be done using the OIDNFormat enumeration type:

Name	Description
OIDN_FORMAT_UNDEFINED	undefined format
OIDN_FORMAT_FLOAT	32-bit single-precision floating point scalar
OIDN_FORMAT_FLOAT[234]	... and [234]-element vector

**Table 3.6** – Supported data formats, i.e., valid constants of type `OIDNFormat`.

## Filter

Filters are the main objects in Open Image Denoise that are responsible for the actual denoising. The library ships with a collection of filters which are optimized for different types of images and use cases. To create a filter object, call

```
OIDNFilter oidnNewFilter(OIDNDevice device, const char* type);
```

where `type` is the name of the filter type to create. The supported filter types are documented later in this section. Once created, filter objects can be retained and released with

```
void oidnRetainFilter(OIDNFilter filter);
void oidnReleaseFilter(OIDNFilter filter);
```

After creating a filter, it needs to be set up by specifying the input and output image buffers, and potentially setting other parameter values as well.

To bind image buffers to the filter, you can use one of the following functions:

```
void oidnSetFilterImage(OIDNFilter filter, const char* name,
                        OIDNBuffer buffer, OIDNFormat format,
                        size_t width, size_t height,
                        size_t byteOffset,
                        size_t bytePixelStride, size_t byteRowStride);

void oidnSetSharedFilterImage(OIDNFilter filter, const char* name,
                              void* ptr, OIDNFormat format,
                              size_t width, size_t height,
                              size_t byteOffset,
                              size_t bytePixelStride, size_t byteRowStride);
```

It is possible to specify either a data buffer object (buffer argument) with the `oidnSetFilterImage` function, or directly a pointer to shared user-managed data (ptr argument) with the `oidnSetSharedFilterImage` function.

In both cases, you must also specify the name of the image parameter to set (name argument, e.g. "color", "output"), the pixel format (format argument), the width and height of the image in number of pixels (width and height arguments), the starting offset of the image data (byteOffset argument), the pixel stride (bytePixelStride argument) and the row stride (byteRowStride argument), in number of bytes. Note that the row stride must be an integer multiple of the pixel stride.

If the pixels and/or rows are stored contiguously (tightly packed without any gaps), you can set `bytePixelStride` and/or `byteRowStride` to 0 to let the library compute the actual strides automatically, as a convenience.

Filters may have parameters other than buffers as well, which you can set and get using the following functions:

```
void oidnSetFilter1b(OIDNFilter filter, const char* name, bool value);
void oidnSetFilter1i(OIDNFilter filter, const char* name, int value);
bool oidnGetFilter1b(OIDNFilter filter, const char* name);
int oidnGetFilter1i(OIDNFilter filter, const char* name);
```

After setting all necessary parameters for the filter, the changes must be committed by calling

```
void oidnCommitFilter(OIDNFilter filter);
```

The parameters can be updated after committing the filter, but it must be re-committed for the changes to take effect.

Finally, an image can be filtered by executing the filter with

```
void oidnExecuteFilter(OIDNFilter filter);
```

which will read the input image data from the specified buffers and produce the denoised output image.

In the following we describe the different filters that are currently implemented in Open Image Denoise.

## RT

The RT (ray tracing) filter is a generic ray tracing denoising filter which is suitable for denoising images rendered with Monte Carlo ray tracing methods like path tracing. The RT filter is based on a deep learning based denoising algorithm, and it aims to provide a good balance between denoising performance and quality.

It accepts either a low dynamic range (LDR) or high dynamic range (HDR) color image as input. Optionally, it also accepts auxiliary feature images, e.g. albedo and normal, which improve the denoising quality, preserving more details in the image.

The filter can be created by passing "RT" to the `oidnNewFilter` function as the filter type. The filter supports the following parameters:

Table 3.7 – Parameters supported by the RT filter.

Type	Format	Name	Default	Description
Image	float3	color		input color image (LDR or HDR)
Image	float3	albedo		input image containing the albedo value of the first hit per pixel; <i>optional</i>
Image	float3	normal		input image containing the normal (world-space or view-space, arbitrary length) of the first hit per pixel; <i>optional</i> , requires setting the albedo image too
Image	float3	output		output image; can be one of the input images
bool		hdr	false	whether the color is HDR
bool		srgb	false	whether the color is encoded with the sRGB (2.2 gamma) curve (LDR only) or is linear; the output will be encoded with the same curve

All specified images must have the same dimensions.

# Chapter 4

## Examples

### Denoise

A minimal working example demonstrating how to use Open Image Denoise can be found at `examples/denoise.cpp`, which uses the C++11 convenience wrappers of the C99 API.

This example is a simple command-line application that denoises the provided image, which can optionally have auxiliary feature images as well (e.g. albedo and normal). The images must be stored in the [Portable FloatMap](#) (PFM) format.

Running `./denoise` without any arguments will bring up a list of command line options.

© 2018–2019 Intel Corporation

Intel, the Intel logo, Xeon, Intel Xeon Phi, and Intel Core are trademarks of Intel Corporation in the U.S. and/or other countries.

\*Other names and brands may be claimed as the property of others.

Optimization Notice: Intel's compilers may or may not optimize to the same degree for non-Intel microprocessors for optimizations that are not unique to Intel microprocessors. These optimizations include SSE2, SSE3, and SSSE3 instruction sets and other optimizations. Intel does not guarantee the availability, functionality, or effectiveness of any optimization on microprocessors not manufactured by Intel. Microprocessor-dependent optimizations in this product are intended for use with Intel microprocessors. Certain optimizations not specific to Intel microarchitecture are reserved for Intel microprocessors. Please refer to the applicable product User and Reference Guides for more information regarding the specific instruction sets covered by this notice.

Notice Revision #20110804